# **Ethos 1.5 new features**

#### **Text Viewer**

Viewer for .txt (text) files, but also for .md (markdown) files




### **Text widget**

.txt (text) or .md (markdown) files can be displayed inside the Text widget




### **Custom checklist**


.txt (text) or .md (markdown) files displayed in Checklists




## Play audio to play audio sequences

Values and Files can be played in sequence within the same function, their order is easily modifiable and cloneable






Conditions (Source or Duration) may be inserted inside the sequence so that the next prompt is played once the condition is true (i.e. to play IMAC sequences)





And it's possible to configure a Reset condition which restarts the sequence from the beginning at any moment.




## **Multiple voices**

Up to 3 voices allowed, system wide. The main voice is used for system prompts, but the other voices can be chosen for the Play audio function or Timer audio actions.









#### **Vars**


The «Var » mix has been removed and replaced by a new « Vars » module :




Up to 64 vars allowed, with multiple values per Var, and multiple actions to modify those values. The range can be driven by another Var.



Those Vars are available on all parameters where the « hamburger » icon appears.




And even in curves!




# **Log Viewer**


Multiple curves ...



With zoom ...



And custom colors ...




## More powerful Free Mix

It was not possible to have multiple weights, or multiple curves inside th previous free mix. Also the actions order is now modifiable.













#### Bluetooth file transfer











### Bluetooth model transfer






#### **Enhanced Trims**

The « Trim » mix has been removed and replaced by a better trim control:


3 modes allowed to control each trim:

- Easy mode : one value for all conditions
- Independant trim per flight mode
- Custom: with conditions and complex programming





5 extra trims can be used in addition to the « normal » 4 trims (6 on some radios). They benefit from the same features as the other trims and they have a condition for Up and Down




#### **Instant Trim**

Long awaited feature!



# Move trim(s) to subtrim(s)

For all trims in one shot ...







... or one trim at a time in its section ...





#### **Trainer from CPPM and SBUS**



The complete System / Wireless screen has been removed and functions moved to where Bluetooth can be used (Trainer / Telemetry / Audio).







## New model wizard improved

Stabilized receivers special mixes automatically created



Channels review before saving the model

